## How to get started with a DTSC-200A?

## Simon - 2024-12-17 - DTSC-200

The DTSC-200A gets connected via a market standard USB-Mini connection. (please make sure it's not just a power cord and includes the data connection wires)

A general product introduction is available here: <u>https://easygen.eu/ats/</u>

The latest Toolkit software for the DTSC-200A is available here: <a href="https://wss.woodward.com/manuals/PGC/SW\_Tools/ToolKit">https://wss.woodward.com/manuals/PGC/SW\_Tools/ToolKit</a>

Please download the device configuration files here: <u>https://easygen.org/configuration\_files/</u>

The following video playlist contains two introduction videos for Toolkit. While most of the Videos were made for a different control, the two Toolkit videos are also valid for the DTSC-200A:

https://youtu.be/zsV8SWC-p7A?list=PLW55kmXY0fHCoZptLxzCvzmB5POGRbfYK

Please have a look into the following document - starting with page 10 on Toolkit: https://wss.woodward.com/manuals/PGC/DTSC\_series/DTSC-200A/01\_Technical\_Manual/37940\_TM\_DTSC-200A\_ Configuration\_B.pdf

Typical issues:

In some cases the USB Driver installation, doesn't get automatically installed. In such cases, please try to install the second driver used for DTSC-200A.

https://wss.woodward.com/manuals/PGC/SW\_Tools/USB\_Drivers

We hope this article helped you to get started with your Woodward DTSC-200A controller!

- タグ
- <u>DTSC-200A</u>